Material Design

UI Elements—Light

STATUS BAR

ui_statusBar_android Y-position is top-aligned (Y: 0px)

- X-position is left-aligned (X: 0px) - Width extends full width of layout Do not adjust height

ui_statusBar_chrome

- X-position is left-aligned — Width extends full width of layout
- Do not adjust height

Element

- - 12:30


Context

V-position is top-aligned (Y: 0px)

ui_appBar

APP BAR

- Z-position behind Status Bar – Y-position is top-aligned (Y: -8px)
- X-position is left-aligned (X: -8px) For accurate width add 16px to desired width Do not adjust height for default state
- ui_appBar_focus - Z-position behind Status Bar – Y-position is top-aligned (Y: -40px) – X-position is left-aligned (X: -40px)
- For accurate width add 80px to desired width For accurate height add 80px to desired height



— Z-position behind App Bar H-position of inset card is left-aligned (X: 0px) H-position of full-width card is left-aligned (X: 10px)

CARDS

ui_card_light

For inset card add 16px to desired width For full-width card add 20px to desired width

For accurate height add 16px to desired height

DROPDOWNS

For accurate height add 16px to desired height


— Z-position equal to App Bar

ui_dropdown

— Y-position is 8px below App Bar's bottom edge

X-position is 8px from layout's left or right edge

For accurate width add 16px to desired width



X-position is left-aligned (X: -8px) For accurate width add 16px to desired width Do not adjust height

SEARCH FIELD

- Z-position behind Status Bar

Y-position is top-aligned (Y: -8px)

ui_searchField_full

ui_searchField_inset

— Z-position behind status bar

- Tablet X-position is 16px from layout's left edge Desktop Y-position is 16px below Status Bar's bottom edge Desktop X-position is 16px from layout's left edge For accurate width add 16px to desired width
- For accurate height add 16px to desired height

— Mobile Y-position is 8px below Status Bar's bottom edge — Mobile X-position is 8px from layout's left and right edge

— Tablet Y-position is 16px below Status Bar's bottom edge

DIVIDERS

ui_divider_dark

SIDE NAV


ui_sideNav_left_light

— Z-position same as content

— Do not adjust height

- Z-position above App Bar Y-position is top-aligned (Y: -40px) X-position is left-aligned (X: -40px) For accurate width add 40px to desired width

For accurate height add 40px to desired height



ui_dialog_light

— Z-position above all content

— Y-position is centered

X-position is centered

ui_sideNav_right_light

— Z-position above App Bar

Y-position is top-aligned (Y: -40px)

X-position is right-aligned (X: -40px)


For accurate width add 40px to desired width

For accurate height add 40px to desired height

- **DIALOG**

- For accurate width add 160px to desired width

- For accurate height add 160px to desired height





Z-position above content


— Do not adjust height

— Do not adjust width

- BUTTON
- ui_buttonCircle_light









Z-position above content — Do not adjust height Do not adjust width

ui_buttonCircle_focus_light





Material Design

UI Elements—Dark

STATUS BAR

ui_statusBar_android

- Y-position is top-aligned (Y: 0px)
- Do not adjust height
- X-position is left-aligned (X: 0px) — Width extends full width of layout
- Element
- 12:30

ui_statusBar_chrome


- V-position is top-aligned (Y: 0px)
- X-position is left-aligned — Width extends full width of layout
- Do not adjust height

Context

APP BAR

- ui_appBar - Z-position behind Status Bar
- Y-position is top-aligned (Y: -8px) X-position is left-aligned (X: -8px) For accurate width add 16px to desired width
- Do not adjust height for default state





ui_appBar_focus


- Z-position behind Status Bar


– Y-position is top-aligned (Y: -40px)

X-position is left-aligned (X: -40px)

- For accurate width add 80px to desired width

For accurate height add 80px to desired height





Z-position behind App Bar


ui_card_dark

CARDS

H-position of inset card is left-aligned (X: 0px)

- H-position of full-width card is left-aligned (X: 10px) - For inset card add 16px to desired width For full-width card add 20px to desired width
- For accurate height add 16px to desired height






— Z-position equal to App Bar — Y-position is 8px below App Bar's bottom edge X-position is 8px from layout's left or right edge

DROPDOWNS

For accurate width add 16px to desired width For accurate height add 16px to desired height

ui_dropdown



Y-position is top-aligned (Y: -8px) X-position is left-aligned (X: -8px)

- Z-position behind Status Bar

ui_searchField_full

SEARCH FIELD

For accurate width add 16px to desired width Do not adjust height

- ui_searchField_inset — Z-position behind status bar — Mobile Y-position is 8px below Status Bar's bottom edge Mobile X-position is 8px from layout's left and right edge — Tablet Y-position is 16px below Status Bar's bottom edge


— Tablet X-position is 16px from layout's left edge

Desktop X-position is 16px from layout's left edge

For accurate width add 16px to desired width

For accurate height add 16px to desired height


Desktop Y-position is 16px below Status Bar's bottom edge



— Z-position same as content — Do not adjust height

DIVIDERS

ui_divider_light



For accurate height add 40px to desired height

SIDE NAV

ui_sideNav_left_dark

Z-position above App Bar

Y-position is top-aligned (Y: -40px)

X-position is left-aligned (X: -40px)

For accurate width add 40px to desired width

ui_sideNav_right_dark


— Z-position above App Bar

Y-position is top-aligned (Y: -40px)

X-position is right-aligned (X: -40px)

For accurate width add 40px to desired width

For accurate height add 40px to desired height





DIALOG ui_dialog_dark


— Z-position above all content


— Y-position is centered

X-position is centered

For accurate width add 160px to desired width

- For accurate height add 160px to desired height





BUTTON

ui_buttonCircle

Z-position above content

— Do not adjust height

— Do not adjust width

- Do not adjust height — Do not adjust width

ui_buttonCircle_focus

Z-position above content

